



Basic maps tutorial

based on [GeoNode Users Guide](#)
for [Data Atlas Fontium](#) platform

Developed by: Aniela Rzaša
Departament of Historical Atlas
Institute of History of the Polish Academy of Sciences
<http://atlasfontium.pl/>
atlasfontium@ihpan.edu.pl

About the tutorial

This tutorial is dedicated to non-advanced Users of the [Data Atlas Fontium](#) platform.

data.atlasfontium.pl is a repository of historical geodata managed by the Department of Historical Atlas (IH PAN). It allows storing historical sources and materials that have a spatial dimension and as such can easily be viewed as maps.

In this manual, we describe how to manage maps.


Tutorial was based on [GeoNode Users Guide](#), where you can find more advanced and detailed information.

About maps

Maps are the basic component of GeoNode, consisting of various layers. They also have other functionalities such as map zoom, layer order, and style.


In this manual, we will create a map based on the uploaded layers. We will make the created map available for public viewing.

Select *Create Map* from the Map menu.



Map creation


Functionalities available in the map creation view:



The background change tool allows you to choose one of available background maps. You can also choose the option without underlay.



Save and share tools

To save the map, click on  and select the Save as ... option.

Save As...×

Thumbnail

Drop or click to import an image

Name

Test map

Description

Test map - description

Close


Save As...

Complete the name and description of the map. If you have a thumbnail, add it by clicking on the gray box or drag the image.


Save the map by clicking the **Save As ...** button


After the map is saved for the first time, the Save option will appear, allowing you to overwrite changes to the map. Each re-use of Save As... will create a new map.

The shared map will always open in the view in which it was saved.




Add layers to the map

To add layers to the map, click on the layer management tool  and select the add layer button:




From the window on the right, select the layer you want to add to your map. To make it easier, use the text filter.




Layers in the map

The added layers appear on the map and on the layer list.



The order in which the layers appear in the map is the same as in the list. In the example above, the layer with labels is under the point layer.


To swap layers, drag the layer to a new place.

The icon  shows the layer's visibility status. After clicking on it, you can exclude the selected layer from displaying.

The appearance of the added layers will be determined by their style. For more information on customizing the appearance of layers, see the [Styling Guide](#).

Layer settings

Choose one of the layers in the list and a toolbar will appear.



Click to zoom the map view to the selected layer.



Click to enable settings for the selected layer.

In the first settings window, you can change the title of the layer in the map and its description.

Remember to save all changes with the  button.

A screenshot of the layer settings form for the layer 'ne_10m_geography_regions_points'. The form has a title bar with a close button (X) and a settings button (wrench). Below the title bar is a toolbar with a save button (floppy disk), a pan icon, an eye icon, and a settings icon. The form fields include: 'Title' (ne_10m_geography_regions_points), 'Name' (geonode:ne_10m_geography_regions_points), 'Description' (No abstract provided), 'Group' (Default), 'Tooltip' (Title), and 'Placement' (Top). Each field has a corresponding save or edit button.


Layer settings

The second view of the layer settings contains display options.

To limit the display at certain zoom levels, select the scale or the maximum and minimum resolution.

If the above fields are completed, the user viewing the map will only see the layer within the specified scale / resolution range while zooming in on the map.

After making changes, save and close the settings window.



ne_10m_geography_regions_points

Format

image/png

WMS Layer tile size

256

Opacity %

100

Visibility limits

Max value (excluded)

Select max value

Min value (included)

Select min value

Limits type

Scale

☒ Transparent

☒ Use cache options

☐ Single Tile



Click to enable layer filtering options. Filtering works the same as the layer data editor filter. Only filtered features will be visible on the map.



Click to show the layer attribute table.



Click to remove the layer from the map.



Click to add additional text, chart, table or counter to the map.




Click to export the layer.




Click to enable the compare tool.

Map sharing


To share the map, click on  and select the *Share* option.



A window will open, it shows link to the currently saved map and a code to embed the map.

To share the map, copy the first link with the button  and send it to the viewers of the map.


To make the map visible to everyone, check its permissions. Click *Explore Maps* and select your map from the list.



Map permissions

Click the **Change permissions of this map** button.

Testowa mapa



Info

Share

Ratings

Comments

Favorite

Title

License

Abstract

Publication Date

Regions

Testowa mapa

Not Specified

Testowy opis

June 2, 2022, 5:26 p.m.

Poland

Download Map

Metadata Detail

Editing Tools

View Map

Map Layers

This map uses the following layers:

ne_10m_lakes

ne_10m_populated_places

ne_10m_geography_regions_points

Permissions

Specify which users can view or modify this map

Change Permissions of this Map

Copy this map

Duplicate this map and use it for your own purposes

Update the map permissions. If you want everyone to see the map, check the **Anyone** parameter. If you are not going to share it, leave the permissions only to yourself. After setting the permissions, click **Apply Changes**.

Set permissions for this resource

People and Groups

Who can view it?

☐ Anyone

The following users:

x example

The following groups:

Who can download it?

Who can change metadata for it?

Who can manage it? (update, delete, change permissions, publish/unpublish it)


Cancel

Apply Changes

Map print

To print the map, go back to the map view by pressing the *View Map* button.

Testowa mapa



Download Map

Metadata Detail

Editing Tools

View Map

Map Layers

This map uses the following layers:

> ne_10m_lakes

> ne_10m_populated_places

> ne_10m_geography_regions_points

Permissions

Specify which users can view or modify this map

Info


Share

Ratings

Comments

Favorite

Map print

Set the map on the view from which you want to make a print.
Click  and choose Print.



Complete the print title and description. Select the resolution, sheet size, and orientation of the page.

Print

Title

Enter a title...

Description

Enter a description...

Resolution:

96 dpi

Layout

Sheet size:

A3

☐ Include legend

☐ Legend on distinct page

☐ Landscape

☒ Portrait

Legend options

Map print

After filling in the required fields, click the **Print** button.

[illegible]

The generated printout will appear. To download it, click .

The generated pdf file will be automatically downloaded by the browser.

